

Nikon D7200

From Snapshots to Great Shots

Learn the best
ways to compose
your pictures!

Get great detail
in your subjects!

Jerod Foster

Nikon D7200:
From
Snapshots to
Great Shots

Jerod Foster



Peachpit
Press

Nikon D7200: From Snapshots to Great Shots

Jerod Foster

Peachpit Press

www.peachpit.com

To report errors, please send a note to errata@peachpit.com

Peachpit Press is a division of Pearson Education
Copyright © 2016 Peachpit Press

All photographs © Jerod Foster except where indicated

Acquisitions Editor: Susan Rimerman
Project Editor: Karyn Johnson
Senior Production Editor: Lisa Brazieal
Development/Copyeditor: Scout Festa
Composition: WolfsonDesign
Proofreader: Steffi Drewes
Indexer: Karin Arrigoni
Cover Image: Jerod Foster
Cover Design: Aren Straiger
Interior Design: Mimi Heft

Notice of Rights

All rights reserved. No part of this book may be reproduced or transmitted in any form by any means, electronic, mechanical, photocopying, recording, or otherwise, without the prior written permission of the publisher. For information on getting permission for reprints and excerpts, contact permissions@peachpit.com.

Notice of Liability

The information in this book is distributed on an “As Is” basis, without warranty. While every precaution has been taken in the preparation of the book, neither the author nor Peachpit shall have any liability to any person or entity with respect to any loss or damage caused or alleged to be caused directly or indirectly by the instructions contained in this book or by the computer software and hardware products described in it.

Trademarks

“From Snapshots to Great Shots” is a trademark, in the U.S. and/or other countries, of Pearson Education, Inc. or its affiliates. Many of the designations used by manufacturers and sellers to distinguish their products are claimed as trademarks. Where those designations appear in this book, and Peachpit was aware of a trademark claim, the designations appear as requested by the owner of the trademark. All other product names and services identified throughout this book are used in editorial fashion only and for the benefit of such companies with no intention of infringement of the trademark. No such use, or the use of any trade name, is intended to convey endorsement or other affiliation with this book.

ISBN-13: 9780134268392

ISBN-10: 0134268393

9 8 7 6 5 4 3 2 1

Printed and bound in the United States of America

Dedication

To my parents, Jay and Marsha Foster.

Acknowledgments

I'm lucky to have such a great production team at Peachpit! Their incredible guidance is what really makes books like these a success! Specifically, I would like to thank Karyn Johnson, Susan Rimerman, Scout Festa, Lisa Brazieal, Steffi Drewes, Karin Arrigoni, Aren Straiger, Mimi Heft, Sara Todd, and Sheila Lease. I've been honored to work with these folks for several great years. I couldn't ask for a better team, and their patience with my travels and assignment work was invaluable in making sure the book stayed on the rails. Thank you, all. I also want to thank Jeff Revell for creating the foundation for what has resulted in a great series of books for many new camera owners, and thanks to my colleague John Batdorff for laying a good path to follow in this series on Nikon cameras.

Thanks also to my friends at Armadillo Camera for their generous support in providing me an early copy of the camera. I can't thank Steve, Larry, Wayne, and Raymond enough for their support, technical insight, and friendship over the years.

Many thanks to the College of Media and Communication at Texas Tech University. I've been lucky the past few years to serve as a professor in the Department of Journalism and Electronic Media, teaching students photography all over the world and getting to share my passion for storytelling with thousands. Thanks especially to Dean David Perlmutter, PhD; Todd Chambers, PhD; and Rob Peaslee, PhD, for understanding how important working and teaching in the photography industry.

Thanks also goes to my wife, Amanda, and my two daughters, Eva and Lola Mae. You are the definition of patience and support. I love you very much!

Finally, thanks to anyone else who had a role in making this project come together. With each book, this list gets longer and longer. Thank you all.

Contents

INTRODUCTION	ix
CHAPTER 1: THE D7200 TOP 12 LIST	1
Twelve Tips to Make Your Shooting More Productive Right Out of the Box	
Poring Over the Picture	2
Poring Over the Camera	4
1. Set the Correct White Balance	6
2. Turn Off the Auto ISO Setting	8
3. Set Your Image Quality	10
4. Set the Appropriate Image Area	12
5. Set Your Focus Point and Mode	13
6. Manual Focus	14
7. Review Your Shots	15
8. Where's the Beep? Custom Focusing Options	19
9. Use the Grid	22
10. Shutter Delay Options	22
11. Oh, Shoot! Reset Options	23
12. Hold Your Camera for Proper Shooting	24
Chapter 1 Assignments	26
CHAPTER 2: FIRST THINGS FIRST	29
A Few Things to Know and Do Before You Begin Taking Pictures	
Poring Over the Picture	30
Choosing the Right Memory Card	32
Formatting Your Memory Card	32
Updating the D7200's Firmware	34
Cleaning the Sensor	36
Using the Right Format: RAW vs. JPEG	37
Lenses and Focal Lengths	41

What Is Exposure?	46
Motion and Depth of Field	49
Chapter 2 Assignments	51
CHAPTER 3: THE AUTO MODES	53
Getting Started with the Scene/Special Effects Modes	
Poring Over the Picture	54
Auto Mode	56
Flash Off Mode	57
Scene Modes	58
Special Effects	69
When You May Not Want to Use Auto Mode	72
Chapter 3 Assignments	74
CHAPTER 4: THE PROFESSIONAL MODES	77
Taking Your Photography to the Next Level	
Poring Over the Picture	78
P: Programmed Auto Mode	80
S: Shutter Priority Mode	85
A: Aperture Priority Mode	91
M: Manual Mode	95
User Settings Mode—Saving Your Favorite Settings to the Mode Dial	98
How I Shoot: My Favorite Camera Settings	99
Chapter 4 Assignments	102
CHAPTER 5: MOVING TARGET	105
How to Shoot When Your Subject Is in Motion	
Poring Over the Picture	106
Stop Right There!	108
Using Shutter Priority (S) Mode to Stop Motion	112
Using Aperture Priority (A) Mode to Isolate Your Subject	115
The ISO Sensitivity Auto Control Trick	116
Keep Them in Focus with Continuous-servo Focus and AF Focus Point Selection	118
Stop and Go with 3D-tracking AF	119
Manual Focus for Anticipated Action	120

Keeping Up with the Continuous Shooting Modes	122
A Sense of Motion	124
Tips for Shooting Action	127
Chapter 5 Assignments	131
CHAPTER 6: PERFECT PORTRAITS	133
Settings and Features to Make Great Portraits	
Poring Over the Picture	134
Automatic Portrait Mode	136
Using Aperture Priority Mode	136
Metering Modes for Portraits	139
Using the AE Lock (Auto Exposure Lock) Feature	141
Focusing: The Eyes Have It	142
Classic Black-and-White Portraits	144
The Portrait Picture Control for Better Skin Tones	145
Detect Faces with Live View	146
Use Fill Flash for Reducing Shadows	146
Portraits on the Move	148
Tips for Shooting Better Portraits	150
Chapter 6 Assignments	159
CHAPTER 7: LANDSCAPE PHOTOGRAPHY	161
Tips, Tools, and Techniques for Taking Beautiful Landscape Photographs	
Poring Over the Picture	162
Sharp Focus: Using a Tripod	164
Selecting the Proper ISO	166
Using Noise Reduction	167
Selecting a White Balance	169
Using the Landscape Picture Control	171
Taming Bright Skies with Exposure Compensation	173
Shooting Amazing Black-and-White Landscapes	176
The Golden Light	178
Where to Place Your Focus	179
Focusing with Live View	181

Smooth Water	182
Directing the Viewer's Eye: A Word About Composition	183
Advanced Techniques to Explore	189
Chapter 7 Assignments	196
CHAPTER 8: MOOD LIGHTING	199
Shooting When the Lights Get Low	
Poring Over the Picture	200
Raising the ISO	202
Using Very High ISOs	204
Stabilizing the Situation	206
Focusing in Low Light	208
Shooting Long Exposures	210
Using the Built-In Flash	212
Compensating for Flash Exposure	215
Reducing Red-Eye	216
Flash and Glass	219
A Few Words About External Flash	219
Chapter 8 Assignments	220
CHAPTER 9: CREATIVE COMPOSITIONS	223
Better Photography Starts with Better Composition	
Poring Over the Picture	224
Depth of Field	226
Angles	228
Point of View	229
Patterns	230
Color	231
Contrasting and Complementing	232
Leading Lines	234
Splitting the Frame	234
Frames Within Frames	236
Chapter 9 Assignments	237

CHAPTER 10: LIGHTS, CAMERA, ACTION	239
Getting the Most out of the D7200's Video Capabilities	
Recording with Live View	240
Dedicating a Second Card to Video	241
Video Quality	242
Sound	244
Playback	246
Focusing	247
Editing	248
Expanding your knowledge	248
Chapter 10 Assignments	249
CHAPTER 11: ADVANCED TECHNIQUES	251
Impress Your Family and Friends	
Poring Over the Picture	252
Spot Meter for More Exposure Control	254
Manual Mode	257
Avoiding Lens Flare	260
Bracketing Exposures	261
Macro Photography	263
Active D-Lighting	265
Conclusion	266
Chapter 11 Assignments	267
INDEX	268

Introduction

Congratulations on your new camera, the Nikon D7200! If you're anything like me, you want to start using your camera as quickly as possible. This book will help you do just that! In a variety of ways, this book will guide you toward making strong, creative images. It's important to know that you already have *the* guide to your camera because it came right in the box: the owner's manual. But don't worry, *Nikon D7200: From Snapshots to Great Shots* is not a rehash of the manual. Rather, it is a resource on photography and creating great images with your new camera. The book highlights important and creative photographic concepts while pointing out techniques and how to achieve different visual elements with the D7200. The following chapters include instructional photographs and anecdotal insight stemming from my own work as a professional photographer and teacher. I have put together a short Q&A to help you get a better understanding of just what it is that you can expect from this book.

Q: Is every camera feature going to be covered?

A: Nope, just the ones I think you need to know in order to start taking great photos. As I said, you already own a great resource that covers every feature of your camera: the owner's manual. (I know, we all hate reading manuals—we want to grab our new camera and start shooting. But if you look at your manual more closely, you'll realize it can actually help you.) A book that just rephrases this information would have been a waste of your time and money. What I did want to write about was how to harness certain camera features to benefit your photography. As you read through this book, you will also see references to specific pages in your owner's manual that are related to the topic being discussed. For example, in Chapter 6 the AE-L button is discussed, but there is more information available on this feature in the manual. I cover the function that applies to our specific needs and give you the page numbers in the manual to explore this function further.

Q: So if I already own the manual, why do I need this book?

A: The manual does a pretty good job of telling you how to use a feature or turn it on in the menus, but it doesn't necessarily tell you why and when you should use it. If you really want to improve your photography, you need to know the whys and the whens to put all of those great camera features to use. To that extent, the manual just isn't going to cut it. It is, however, a great resource on the camera's features, and for that reason I treat it like a companion to this book. You already own it, so why not get something of value from it?

Q: What can I expect to learn from this book?

A: Hopefully, you will learn how to take great photographs. My goal, and the reason the book is laid out the way it is, is to guide you through the basics of photography as they relate to different situations and scenarios. By using the features of your D7200 and this book, you will learn about aperture, shutter speed, ISO, lens selection, depth of field, and many other photographic concepts. You will also find plenty of large full-page photos that include shooting data and comments from me so you can see how all of the photography fundamentals come together to make great images. Meanwhile, you will be learning how your camera works and how to apply its functions and features to your photography.

Q: Do I really need to do the assignments?

A: At the end of most chapters, you will find shooting assignments, where I give you some suggestions on how you can apply the lessons of the chapter to help reinforce everything you just learned. Can I make you do them? No, but let's face it—using the camera is much more fun than reading about it, so the assignments are a way of taking a little break after each chapter, having some fun, and trying out your new chops.

Q: Should I read the book straight through, or can I skip around from chapter to chapter?

A: Here's the easy answer: yes and no. No, skipping around the whole time isn't the best idea, because the first four chapters give you the basic information that you need to know about your camera. These are the building blocks of using the D7200. After that, yes, you can move around the book as you see fit, because the following chapters are written to stand on their own as guides to specific types of photography or shooting situations. So you can bounce from portraits to landscapes and then maybe to a little action photography. It's all about your needs and how you want to address them. Or, you can read the book straight through. The choice is up to you.

Q: Is that it?

A: One last thought before you dive into the first chapter. My goal in writing this book has been to give you a resource that will help you create great photographs with your Nikon D7200. Learning the basics is vital, but playing with them is what makes the photographer. Photography, like most things, takes time to master and requires practice. One of the most important things I tell my students and others about my own photography work is that I'm still learning. Always remember that it's not the camera that makes beautiful photographs—it's the person using it. Photography is one of those activities that let you explore, no matter if you are traveling or shooting your child's birthday party. So enjoy the experience, learn from your mistakes (which I encourage you to make), and take your snapshots to another level—to great shots.



ISO 400 • 1/40 sec. •
f/4.5 • 51mm lens

4

The Professional Modes

Taking Your Photography to the Next Level

If you talk to professional photographers, you will find that the majority of them use a few selective modes that offer the greatest amount of control over their photography. To anyone who has been involved with photography for any period of time, these modes are the backbones of the art. They allow you to influence two of the most important factors in taking great photographs: *aperture* and *shutter speed*. To access these modes, you simply turn the Mode dial to one of the letter-designated modes and begin shooting. But wouldn't it be nice to know exactly what those modes control and how to make them do our bidding? Well, if you really want to take that next step in controlling your photography, it is essential that you understand not only how to control these modes but why you are controlling them. So let's move that Mode dial to the first of our professional modes: Programmed Auto mode.

Poring Over the Picture

— I used a low ISO with a tripod to guarantee a high-quality image free of camera shake.

I love spending time around Poage Lake, near South Fork, Colorado. Mountain lakes are great places to explore photographically, and the Rio Grande National Forest contains many. On a recent visit, I walked around the lake close to sunset. The light was warm and the colors were vibrant.

ISO 100 • 1/6 sec. •
f/22 • 32mm lens



The late evening light is actually easier to expose for than middle-of-the-day light. It looks more engaging and makes colors pop.

The wide-angle lens allowed me to use the foreground timber to lead the eye through the frame.

P: Programmed Auto Mode



As the saying jokingly goes, “P is for *professional!*” Programmed Auto mode, or P mode, is a great mode to become familiar with as you transition from the automatic or scene modes (**Figure 4.1**) to Aperture Priority, Shutter Priority, or Manual mode. There is a reason that Programmed Auto mode is only one click away from the automatic modes: With respect to apertures and shutter speeds, the camera is doing most of the thinking for you. So if that is the case, why even bother with P mode?



Figure 4.1 Use Programmed Auto mode for flexible control and as a great place to start learning the professional modes.

ISO 100 • 1/125 sec. • f/11 • 85mm lens

First, let me say that I rarely use Programmed Auto mode because it just doesn't give as much control over the image-making process as the other professional modes. However, we all start somewhere, and much like many of you, I started fully automatic, moved to Programmed

Auto mode, and now hang out in Aperture Priority most of the time. There are still occasions when Programmed Auto mode comes in handy, like when I am shooting in widely changing lighting conditions and I don't have the time to think through all of my options, or I'm not very concerned with having ultimate control of the scene. Think of a picnic outdoors in a partial shade and sun environment. I want great-looking pictures, but I'm not looking for anything to hang in a museum. If that's the scenario, why choose P mode over one of the scene modes? Because it gives me choices and control that none of the scene modes can deliver.

Manual Callout

To see available settings for each mode, check out the table on pages 51–61 of your owner's manual.

When to use Programmed Auto (P) mode instead of the automatic scene and effects modes

It's graduation time, and you're ready to move on to a more advanced mode but not quite ready to jump in with both feet. When does Programmed Auto mode come in handy?

- When shooting in a casual environment where quick adjustments are needed.
- When you want more control over the ISO.
- If you want to make corrections to the white balance.
- When you want to take advantage of the Flexible Program mode and quickly achieve different combinations of shutter speed and aperture. Move the main Command dial to the left for small apertures to increase depth of field, or rotate the dial to the right for large apertures to create a shallow depth of field.

Let's go back to our picnic scenario. As I said, the light is moving from deep shadow to bright sunlight, which means that the camera is trying to balance our three photo factors (ISO, aperture, and shutter speed) to make a good exposure. From Chapter 1, we know that Auto ISO is generally not what we want except when shooting in a fully automatic mode, so we have already turned that feature off (you did turn it off, didn't you?). Well, in P mode, you can choose which ISO you would like the camera to base its exposure on. The lower the ISO number, the better the quality of photographs, but the less light sensitive the camera becomes. It's a balancing act, with the main goal always being to keep the ISO as low as possible—too low an ISO, and we will get camera shake in our images

from a long shutter speed; too high an ISO, and we will have an unacceptable amount of digital noise (Figures 4.2 and 4.3). For now, let's go ahead and select ISO 400 so that we provide enough sensitivity for those shadows while allowing the camera to use shutter speeds that are fast enough to stop motion.

Figure 4.2

Look closely and you'll notice that the image is grainy or has small pixels. That's digital noise. Now, look at the same image taken at a lower ISO.

ISO 6400 • 1/400 sec. •
f/9 • 28mm lens



Figure 4.3

Notice the detail in the shadows and how little noise there is in the image.

ISO 100 • 1/25 sec. •
f/4.5 • 28mm lens



Starting points for ISO selection

Many years ago, camera manufacturers were racing to create cameras with more megapixels. Today, the digital race is all about higher ISO (even though the number of megapixels packed onto sensors keeps growing). Photographers want to be able to shoot in lower light conditions without the risk of digital noise. There is a lot of discussion concerning ISO in this and other chapters, but it might be helpful if you know where your starting points should be for your ISO settings. The first thing you should always try to do is use the lowest possible ISO setting. Your D7200 has a working range of 100–25600. That being said, here are good starting points for your ISO settings:

- 100: Bright, sunny day.
- 200: Hazy or outdoor shade on a sunny day.
- 400: Indoor lighting at night or cloudy conditions outside.
- 800: Late night, low-light conditions or sports arenas at night.
- 1600: Very low light; possibly candlelight or events where no flash is allowed.
- 3200–6400: Extremely low light (some digital noise will be present; however, less than ever before).
- 12800–25600: When you need night vision (just joking). There may be very few situations dark enough where you need these extremely high ISOs. Noise will be very evident.

These are just suggestions; you'll have to adjust as necessary. Your ISO selection will depend on a number of factors that will be discussed later in the book.

With the ISO selected, we can now make use of the other controls built into Programmed Auto mode. By rotating the main Command dial, we now have the ability to shift the program settings. Remember that your camera is using the internal meter to pick what it deems suitable exposure values, but sometimes it doesn't know what it's looking at and how you want those values applied (**Figures 4.4** and **4.5**). With the Flexible Program mode, you can influence what the shot will look like. Do you need faster shutter speeds in order to stop the action? Just turn the main Command dial to the right. Do you want a smaller aperture so that you get a narrow depth of field? Turn the dial to the left until you get the desired aperture. The camera shifts the shutter speed and aperture accordingly to get a proper exposure.

Figure 4.4

In this image the shutter speed was faster because the image contains many bright values, such as the water. Since the image is lighter, the camera needs less time to expose, so the shutter opens and closes very quickly in Programmed Auto—in this case, over 1/100 of a second quicker than in Figure 4.5.

ISO 100 • 1/160 sec. •
f/11 • 44mm lens



Figure 4.5

By zooming in on the vegetation in the middle of the river, the image becomes darker than in Figure 4.4 because there is less of the bright water. The camera needs more light to properly expose the image, so the shutter is left open longer.

ISO 100 • 1/50 sec. •
f/11 • 62mm lens



You will also notice that a small star will appear above the letter P in the viewfinder and the rear display if you rotate the main Command dial. This star is an indication that you modified the exposure from the one the camera chose. To go back to the default Programmed Auto exposure, simply turn the dial until the star goes away or switch to a different mode and then back to P mode again.

Let's set up the camera for Programmed Auto mode and see how we can make all of this come together.

Setting up and shooting in Programmed Auto mode

1. Turn your camera on, and then turn the Mode dial to align the P with the indicator line.
2. Select your ISO by pressing and holding the ISO button on the back left of the camera while rotating the main Command dial with your thumb.
3. The ISO will appear on the top display. Choose your desired ISO, and release the ISO button on the left to lock in the change.
4. Point the camera at your subject, and then activate the camera meter by depressing the shutter button halfway.
5. View the exposure information in the bottom area of the viewfinder or by looking at the top display panel.
6. While the meter is activated, use your thumb to roll the main Command dial left and right to see the changed exposure values.
7. Select the exposure that is right for you and start clicking. (Don't worry if you aren't sure what the right exposure is yet. We will work on making the right choices for those great shots beginning with the next chapter.)



S: Shutter Priority Mode




S mode is what we photographers commonly refer to as Shutter Priority mode. Just as the name implies, it is the mode that prioritizes or places major emphasis on the shutter speed above all other camera settings (**Figure 4.6**).

Just as with Programmed Auto mode, Shutter Priority mode gives us more freedom to control certain aspects of our photography. In this case, we are talking about shutter speed. The selected shutter speed determines just how long you expose your camera's sensor to light. The longer it remains open, the more time your sensor has to gather light.

Figure 4.6

Shutter Priority mode is great for freezing or showing motion. Use this mode when your shutter speed is of utmost importance.

ISO 200 • 1/1250 sec. •
f/2.8 • 200mm lens



The shutter speed also, to a large degree, determines how sharp your photographs are. Even though an image may appear sharply in focus, any movement by the subject or the camera while the shutter is open can blur the image. If you think about it, when you are trying to show motion, you sometimes want a slower shutter speed because it blurs the image. When you want to freeze the action, you want a faster shutter speed.

A good rule of thumb for avoiding blurry images as a result of camera movement is to always use a shutter speed as fast as or faster than your focal length. For instance, if I'm out photographing my daughter with an 80mm lens, then I'll want to make sure my shutter speed is at least 1/125 of a second, taking into account that the camera is not full frame, so the actual focal length is greater than the focal length of the lens. Anything less than that might cause camera shake (even if you're equipped with biceps as big as Popeye's). The D7200 has a 1.5x magnification, so if your focal length is 100mm, you hypothetically shouldn't shoot less than 1/150 of a second.

Shutter speeds

A *slow* shutter speed refers to leaving the shutter open for a long period of time—like 1/30 of a second or more. A *fast* shutter speed means that the shutter is open for a very short period of time—like 1/250 of a second or less. A faster shutter speed is used to stop motion, and a slower shutter speed is used to show motion.

When to use Shutter Priority (S) mode

- When working with fast-moving subjects and you want to freeze the action (**Figure 4.7**); much more on this in Chapter 5
- When you want to emphasize movement in your subject with motion blur (**Figure 4.8**)
- When you want to use a long exposure to gather light over a long period of time (**Figure 4.9**)
- When you want to create that smooth-looking water in a waterfall or rapids in a creek or river (**Figure 4.10**)

Figure 4.7
Freezing motion is a result of a very fast shutter speed.

ISO 100 • 1/1250 sec. •
f/2.8 • 160mm lens



Figure 4.8
Emphasizing motion can be creatively achieved by using relatively slow shutter speeds. This technique, known as panning, is successful when the background is laterally blurred and most of the subject remains in focus.

ISO 100 • 1/160 sec. •
f/8 • 400mm lens





Figure 4.9
To capture the red glow of the Texas Tech logo on the barn, I needed to expose it against a darker sky after sunset. The 15-second exposure necessitated the use of a tripod and shutter release.

ISO 100 • 15 sec. •
f/14 • 17mm lens




Figure 4.10 Flowing water is always fun to shoot. I used a tripod and shutter release to ensure that my own movement would not blur the image at this motion-emphasizing shutter speed.

ISO 100 • 5 sec. • f/22 • 24mm lens

As you can see, the subject of your photo usually determines whether or not you will use Shutter Priority mode. It is important that you be able to previsualize the result of using a particular shutter speed. The great thing about shooting with digital cameras is that you get instant feedback by viewing your shot on the LCD. But what if your subject won't give you a do-over? Such is often the case when shooting sporting events. It's not like you can go ask your daughter to score another goal in her soccer game because your photograph was blurry from a slow shutter speed. This is why it's important to know what those speeds represent in terms of their capabilities to stop the action and deliver a blur-free shot.

First, let's examine just how much control you have over the shutter speeds. The D7200 has a shutter speed range from 1/8000 of a second all the way down to 30 seconds. With that much latitude, you should have enough control to capture almost any subject. The other thing to think about is that Shutter Priority mode is considered a semiautomatic mode. That means that you are taking control over one aspect of the total exposure while the camera handles the other. In this instance, you are controlling the shutter speed and the camera is controlling the aperture. This is important, because there will be times that you want to use a particular shutter speed but your lens won't be able to accommodate your request.

For example, you might encounter this problem when shooting in low-light situations: If you are shooting a fast-moving subject that will blur at a shutter speed slower than 1/125 of a second but your lens's largest aperture is f/3.5, you might find that your aperture display in your viewfinder and the rear LCD panel will blink. This is your warning that there won't be enough light available for the shot—due to the limitations of the lens—so your picture will be underexposed. Your only remedy is to increase your ISO to accommodate the shutter speed needed.

Another case where you might run into this situation is when you are shooting moving water. To get that look of smooth, flowing water, it's usually necessary to use a shutter speed at least as slow as 1/15 of a second. If your waterfall is in full sunlight, the aperture value might blink again because the lens you are using only stops down to f/22 at its smallest opening. In this instance, your camera is warning you that you will be overexposing your image. There are workarounds for these problems, which we will discuss later, but it is important to know that there can be limitations when using Shutter Priority mode.

Setting up and shooting in Shutter Priority mode

1. Turn your camera on, and then turn the Mode dial to align the S with the indicator line.
2. Select your ISO by pressing and holding the ISO button on the back left of the camera while rotating the main Command dial with your thumb.
3. The ISO will appear on the top display. Choose your desired ISO, and release the ISO button on the left to lock in the change.

4. Point the camera at your subject, and then activate the camera meter by depressing the shutter button halfway.
5. View the exposure information in the bottom area of the viewfinder or by looking at the top display panel.
6. While the meter is activated, use your thumb to roll the main Command dial left and right to see the changed exposure values. Roll the dial to the right for faster shutter speeds and to the left for slower speeds.



A: Aperture Priority Mode



Probably the mode most widely used by professional photographers, Aperture Priority is my personal favorite, and I believe that it will quickly become one of yours. Aperture Priority mode is also deemed a semiautomatic mode because it allows you to once again control one factor of exposure while the camera adjusts for the other (Figure 4.11).

Why is this one of my favorite modes? It's because the aperture of your lens dictates depth of field. Depth of field, along with composition, is a major factor in how you direct attention to what matters in your image. It is the controlling factor of how much area in your image is sharp. If you want to isolate a subject from the background, such as when shooting a portrait, you can use a large aperture (low f-stop number) to keep the focus on your subject and make both the foreground and background blurry. If you want to keep the entire scene sharply focused, as with a landscape scene, then using a small aperture (high f-stop number) will render the greatest amount of depth of field possible.



Figure 4.11
Use Aperture Priority mode when you need to control depth of field. I shoot more in this mode than in the others.

ISO 100 • 1/800 sec. •
f/4.5 • 70mm lens

When to use Aperture Priority (A) mode

- When shooting portraits or wildlife (Figure 4.12)
- When shooting most landscape photography (Figure 4.13)
- When shooting in bright skies and silhouetting an image (Figure 4.14)
- When shooting cityscape photography, which often benefits from a large depth of field (Figure 4.15)

Figure 4.12

No matter the size, I often use Aperture Priority to photograph wildlife, which allows me to blur the background and maintain a fast shutter speed if they decide to move quickly.

ISO 100 • 1/320 sec. • f/4 • 105mm lens



Figure 4.13

A smaller aperture setting brings sharpness to near and far objects.

ISO 100 • 1/30 sec. • f/16 • 17mm lens





Figure 4.14
Using a very small aperture, I was able to create a small sunburst behind this outcrop of silhouetted oaks. Typically $f/11$ or higher will do the trick! Give it a try. The key ingredient is a clear sky, since clouds will diffuse the sun.

ISO 100 • 1/100 sec. • $f/13$ • 17mm lens



Figure 4.15
I wanted the foreground as well as the background in focus, so I used a wide-angle lens combined with a small aperture to maintain focus throughout the image. This is called a deep depth of field. The aperture was closed down enough to slow the shutter speed and blur the passing cars.

ISO 200 • 1/15 sec. • $f/11$ • 28mm lens

F-stops and aperture

As discussed earlier, the numeric value of your lens aperture is described as an *f-stop*. The *f-stop* is one of those old photography terms that, technically, relates to the focal length of the lens (e.g., 200mm) divided by the effective aperture diameter. These measurements are defined as “stops” and work incrementally with your shutter speed to determine proper exposure. Older camera lenses used one-stop increments to assist in exposure adjustments, such as 1.4, 2, 2.8, 4, 5.6, 8, 11, 16, and 22. Each stop represents about half the amount of light entering the lens iris as the larger stop before it. Today, most lenses don’t have *f-stop* markings, since all adjustments to this setting are performed via the camera’s electronics. The stops are also now typically divided into 1/3-stop increments to allow much finer adjustments to exposures, as well as to match the incremental values of your camera’s ISO settings, which are also adjusted in 1/3-stop increments.

I strongly recommend knowing your lens’s aperture rating. Every lens has a marking on it with a number; $f/1.4$, $f/2.8$, or $f/5.6$ are all very common maximum aperture sizes. This number simply means the largest aperture your lens supports is $f/1.4$, $f/2.8$, or $f/5.6$, respectively. The D7200 kit ships with a standard 18–140mm lens with an $f/3.5$ – $f/5.6$ variable maximum aperture (**Figure 4.16**).

Knowing the limits of your lens aperture is crucial when using Aperture Priority. As a general rule, the lower the number on the lens, the “faster” it is (because it allows more light in to expose the image, thus reducing the amount of shutter time) and the sharper the image is. Typically, fast lenses are heavier and more expensive, but they’re well worth the investment if you find yourself shooting in low-light conditions. The larger the aperture is, the better the exposure without having to increase ISO and introduce digital noise.

On the other hand, bright scenes require the use of a small aperture (such as $f/16$ or $f/22$), especially if you want to use a slower shutter speed. That small opening reduces the amount of incoming light, and this reduction of light requires that the shutter stay open longer.



Figure 4.16 It’s important to know the focal range and maximum aperture of your lens.

Zoom lenses and maximum apertures

Some zoom lenses (like the 18–140mm kit lens) have a variable maximum aperture. This means that the largest opening will change depending on the zoom setting. In the example of the 18–140mm zoom, the lens has a maximum aperture of $f/3.5$ at 18mm and only $f/5.6$ when the lens is zoomed out to 140mm.

Setting up and shooting in Aperture Priority mode

1. Turn your camera on, and then turn the Mode dial to align the A with the indicator line.
2. Select your ISO by pressing and holding the ISO button on the back left of the camera while rotating the main Command dial with your thumb.
3. The ISO will appear on the top display. Choose your desired ISO, and release the ISO button on the left to lock in the change.
4. Point the camera at your subject, and then activate the camera meter by depressing the shutter button halfway.
5. View the exposure information in the bottom area of the viewfinder or by looking at the top display panel.
6. While the meter is activated, use your finger to roll the Sub-command dial left and right to see the changed exposure values. Roll the dial to the right for a smaller aperture (higher f-stop number) and to the left for a larger aperture (lower f-stop number).



M: Manual Mode



Manual mode is all about control. Keep in mind that this mode was not designed for those of us who want to go on autopilot and shoot to our heart's content. It was designed to allow the photographer to take complete control of shutter speed and aperture (**Figure 4.17**). The camera doesn't do any of the work for you.



Figure 4.17
For ultimate control of shutter speed and aperture, use Manual mode.

ISO 400 • 1/100 sec. •
f/5.6 • 85mm lens

When you have your camera set to Manual (M) mode, the camera meter will give you a reading of the scene you are photographing. It's your job, though, to set both the f-stop (aperture) and the shutter speed to achieve a correct exposure. If you need a faster shutter speed, you will have to make the reciprocal change to your f-stop. Using any other mode, such as Shutter Priority or Aperture Priority, would mean that you just have to worry about one of these changes, but Manual mode means you have to do it all yourself. This can be a little challenging at first, but after a while you will have a complete understanding of how each change affects your exposure, which will, in turn, improve the way that you use the other modes.

When to use Manual (M) mode

- When lighting and exposure get tricky (**Figure 4.18**). Shooting lit-up architecture at nighttime can often confuse the meter, for example. The wonderful thing about your D7200 is that it has an incredible ISO range with relatively low digital noise.
- When your environment is fooling your light meter and you need to maintain a certain exposure setting (**Figure 4.19**). Beaches and snow are always a challenge for light meters. Whenever I'm shooting something in snow I find myself switching over to Manual mode.
- When shooting silhouetted subjects, which requires overriding the camera's meter readings (**Figure 4.20**).

Figure 4.18
For this shot of a Spanish train terminal, I increased my ISO and metered where the light was hitting below. I left my aperture fairly open to draw in as much light as possible for a quick handheld exposure.

ISO 1600 • 1/50 sec. • f/4 • 24mm lens






Figure 4.19
A good rule of thumb in snow is to bump your exposure up one stop in exposure, two if it's really sunny. That should get you closer to the correct exposure.

ISO 200 • 1/500 sec. •
f/8 • 150mm lens



Figure 4.20
I used Manual mode to expose for the bright sky, silhouetting the mountain layers below and avoiding overexposing the orange clouds.

ISO 200 • 1/250 sec. •
f/4 • 200mm lens

Setting up and shooting in Manual mode

1. Turn your camera on, and then turn the Mode dial to align the M with the indicator line.
2. Select your ISO by pressing and holding the ISO button on the back left of the camera while rotating the main Command dial with your thumb.
3. The ISO will appear on the top display. Choose your desired ISO, and release the ISO button on the left to lock in the change.
4. Point the camera at your subject, and then activate the camera meter by depressing the shutter button halfway.
5. View the exposure information in the bottom area of the viewfinder or by looking at the top display panel.
6. To set your exposure using shutter speed, while the meter is activated, use your thumb to roll the main Command dial left and right to change your shutter speed value until the exposure mark is lined up with the zero mark. The exposure information is displayed in the viewfinder using a scale with marks that run from -2 to +2 stops with 0 indicating proper exposure. As the indicator moves to the left, the image is being underexposed, or getting darker. Move the indicator to the right and the image is being overexposed, or getting brighter.
7. To set your exposure using the aperture, while the meter is activated, use your finger to roll the Sub-command dial left and right to see the changed exposure values. Roll the dial to the right for a smaller aperture (higher f-stop number) and to the left for a larger aperture (lower f-stop number).

Overriding the Meter

You might have good reasons to want to overexpose or underexpose an image. For instance, I'll often underexpose my images by a third of a stop to ensure that extreme highlights retain some detail. This is just one of many creative reasons for adjusting your exposure differently than is suggested by the meter.


User Settings Mode—Saving Your Favorite Settings to the Mode Dial



User settings are a great feature if you're looking to have your favorite settings at the turn of a dial. These are located on the dial as U1 and U2. If you have a group of settings that you find you are using often and you want to have them close at hand, then these modes are handy for you.

Establishing User Settings

1. First, set the camera to your favorite settings, under any of the semiautomatic modes or Manual mode, adjusting aperture, shutter speed, ISO, flash, focus point, metering, and/or bracketing.
2. Go to the Setup menu, and click Save User Settings (A).
3. Highlight and click OK on Save to U1 or Save to U2 (B), then click OK on Save Settings to finalize your selection.
4. When you want to use those settings again, just rotate the top dial to U1 or U2, and the camera will choose your saved settings so that you're ready to go.



For more on setting up user modes, see page 62 of your owner's manual.

How I Shoot: My Favorite Camera Settings

I'm generally a nature and editorial assignment photographer, but like many of you, I enjoy photographing everything. There's very little that doesn't interest me. I have found throughout the years that I primarily use the Aperture Priority mode. Why? Often when I'm on assignment, I don't have time to worry about every single variable, and I've found that focusing on the aperture has given me the control I need for 80 percent of my photography. If I want an image to have a shallow depth of field, then I'll use a large aperture, such as f/2.8; if I'm shooting a landscape and I need a greater depth of field, I'll use a smaller aperture, such as f/16.

But sometimes Aperture Priority just doesn't work. Maybe the lighting is tricky or it's close but not quite right. In those cases I'll switch over to Manual mode. Almost all the landscape photography that I've shot during the golden hours was done in Manual mode

because the light changes very quickly. Likewise, when I'm using studio lights, I'm in Manual mode because of the amount of control I have over the entire lighting situation.

Each photographer has a different way of doing things. No single approach is necessarily better than another. In the end, it's about creating your own system so that you're consistent. When you're consistent, you can measure results and then make changes accordingly.

When I first started photographing in Aperture Priority, the biggest mistake I made was shooting with much too slow a shutter speed. I would get blurry pictures and ask myself, "How did this happen? They looked super sharp when I took them." I would then look at the metadata (image information) and see that I had shot the blurry image at 1/30 of a second, way too slow for handholding a camera. So I learned my lesson and started shooting a little faster, and my results improved immensely. Essentially, I learned to keep an eye not only on my aperture while shooting in Aperture Priority, but on my shutter speed as well.

Doing things consistently and measuring results is a great way to improve your photography. Don't ignore the metadata; it's very helpful in understanding why an image looks a certain way and learning how to change your setting the next time to make the image stronger.

Although the other camera modes have their place, I think you will find that most professional photographers use the Aperture Priority and Shutter Priority modes for most of their shooting.

One big concern that I have when I am setting up my camera is just how low I can keep my ISO. This is always a priority for me, because a low ISO will deliver the cleanest image. I raise the ISO only as a last resort because each increase in sensitivity is an opportunity for more digital noise to enter my image.

To make quick changes while I shoot, I often use the Exposure Compensation feature (covered in Chapter 7) so that I can make small over- and underexposure changes. This is different than changing the aperture or shutter; it is more like fooling the camera meter into thinking the scene is brighter or darker than it actually is. To get to this function quickly, I simply press the Exposure Compensation button, right next to the shutter button, and then dial in the desired amount of compensation using the main Command dial. If you can't get the exact exposure you want with aperture and speed alone, make little adjustments to the exposure compensation.

One of the reasons some people change their exposure is to make corrections when there are "blinkies" in the rear LCD. Blinkies are the warning signal that part of the image has been overexposed to the point that there is no longer any detail in the highlights. When the highlight alert feature is turned on, the display will flash wherever the potential exists for overexposure. The black-and-white flashing will only appear in areas of your picture that are in danger of overexposure.

Setting up the highlight alert feature

1. Press the Menu button, and then use the Multi-selector to access the Playback menu.
2. Once in the Playback menu, move the Multi-selector to Playback Display Options and press OK (A).
3. Move the Multi-selector down to select the Highlights option. Move the Multi-selector to the right to place a check mark next to the word Highlights (B).
4. Press OK on the Multi-selector to lock in your change.



Once the highlights warning is turned on, use it to check your images on the back of the LCD after taking a shot. If you see an area that is blinking, try setting exposure compensation to an underexposed setting like $-1/3$ or $-2/3$ stops and take another photo, checking the result on the screen. Don't make yourself crazy trying to get rid of every single blinking area. It is easy enough to add some black back into your photo later using post-processing software, and you don't want to underexpose the rest of the image because there is one blown-out highlight.

Sometimes, such as when shooting into the sun, the warning will blink no matter how much you adjust the exposure because there is just no detail in the highlight. On the contrary, if you're shooting a white wedding dress and the entire dress is blinking, then you have no detail in the dress and the bride will not be happy. Use your best judgment to determine if the warning is alerting you to an area where you want to retain highlight detail. If you are not sure what the perfect exposure is and you have to get a good shot, try bracketing your exposure. We will talk more about this in later chapters.

As you work your way through the coming chapters, you will see other tips and tricks to use in your daily photography, but the most important advice I can give is to take the time to understand the features of your camera so that you can leverage the technology in a knowledgeable way. This will pay off in better photographs.

Chapter 4 Assignments

This will be more of a mental challenge than anything else, but you should put a lot of work into these assignments, because the information covered in this chapter will define how you work with your camera from this point on. Granted, there may be times that you just want to grab some quick pictures and will resort to the automatic scene modes, but to get serious with your photography, you will want to learn the professional modes inside and out.

Starting off with Programmed Auto mode

Set your camera on P mode and start shooting. Become familiar with the adjustments you can make to your exposure by turning the main Command dial. Shoot in bright sun, deep shade, indoors, anywhere that you have different types and intensities of light. While you are shooting, make sure that you keep an eye on your ISO and raise or lower it according to your environment.

Learning to control time with Shutter Priority mode

Find some moving subjects, and then set your camera to S mode. Have someone ride a bike back and forth, or even just photograph cars as they go by. Start with a slow shutter speed of around 1/30 of a second, and then start shooting with faster and faster shutter speeds. Keep shooting until you can freeze the action.

Now find something that isn't moving, like a flower. Start with your shutter speed at something fast like 1/500 of a second, and then work your way down. Don't brace the camera on a steady surface. Just try to shoot as slowly as possible, down to about 1/4 of a second. The point is to see how well you can handhold your camera before you start introducing hand shake into the image, making it appear soft and somewhat unfocused.

Controlling depth of field with Aperture Priority mode

The name of the game with Aperture Priority mode is depth of field. Set up three items at varying distances from you, maybe chess pieces or something similar. Now set your zoom on a focal length of 50mm while focusing on the middle item. Set your camera to the largest aperture your lens will allow. Remember that "large aperture" means a low f-stop number, like f/3.5, and "small aperture" means a high f-stop, like f/22. Now take a photo. While still focusing on the middle subject, set your camera to the smallest aperture your lens will allow and take another photo. Now compare the depth of field between the two images.

Giving and taking with Manual mode

Manual mode is not going to require a lot of work, but you should pay close attention to your results. Go outside on a sunny day, and with the camera in Manual mode, set your ISO to 100, your shutter speed to $1/125$ of a second, and your aperture to $f/16$. Now press your shutter release button to get a meter reading. You should be pretty close to that zero mark. If not, make small adjustments to one of your settings until it hits that mark.

Here is where the fun begins. Start moving your shutter speed slower, to $1/60$, and then set your aperture to $f/22$. Now go the other way. Set your aperture on $f/8$ and your shutter speed to $1/500$. Review your images. If all went well, all the exposures should look the same. This is because you balanced the light with reciprocal changes to the aperture and shutter speed.

Now go back to our original setting of $1/125$ at $f/16$, and try moving the shutter speed without changing the aperture. Just make $1/3$ -stop changes ($1/125$ to $1/100$ to $1/80$ to $1/60$), and then review your images to see what a $1/3$ stop of overexposure looks like. Then do the same thing going the opposite way. It's hard to know if you want to over- or underexpose a scene until you have actually done it and seen the results.

With each of the assignments, make sure that you keep track of your modes and exposures so that you can compare them with the image. If you are using software to review your images, you should also be able to check the camera settings that are embedded within the image's metadata.

Share your results with the book's Flickr group!

Join the group here: [flickr.com/groups/nikond7200_fromsnapshotstogreatshots](https://www.flickr.com/groups/nikond7200_fromsnapshotstogreatshots)

Index

1080i video, 242
1080p video, 242

A

accessories

- cable release, 165, 210, 259
- cables, 246
- filters. *See* filters
- lenses. *See* lenses
- tripods. *See* tripods

accessory shoe, 4

accessory terminal, 5

action shots, 105–131. *See also* motion

- Aperture Priority mode, 115–116

- considerations, 105

- focus, 120–121

- ISO Sensitivity setting, 116–117

- motion blur. *See* motion blur

- portraits, 148–149

- shutter speed and, 49, 50, 106, 108–117

- Sports mode, 62

- stopping motion, 112–114

- subject speed, 110

- tips for, 127–130

Active D-Lighting feature, 71, 73, 265–266

AE/AF Lock button, 3

AE-L (Automatic Exposure Lock) function, 141–142, 255

AF button, 2, 118

AF-A mode, 61, 62, 72

AF-area mode, 118–119

AF-assist illuminator, 2, 14, 19, 209

AF-C (Continuous-servo AF) mode, 72, 118–119

AF-S (Single-servo AF) mode, 13–14, 72, 142–144

angles, 228

animals

- pets, 68

- wildlife, 45, 92, 243

aperture

- blurring and, 49, 115–116

- considerations, 45, 98–100

- depth of field and, 49, 91–95, 115–116

- exposure and, 47, 48–49

- f-stops and, 47, 48–49, 94

- isolating subject, 50

- lighting and, 94

- portraits, 136–139

- reflections and, 228

- shutter speed and, 210

- size, 91–95

Aperture Priority (A) mode

- action shots, 115–116

- blurred backgrounds, 115, 136–137

- considerations, 91–95, 99, 100, 226

- flash and, 212

- macro photography, 263–264

- portraits, 136–139

- shooting in, 95

- vs. Shutter Priority mode, 115–116

- shutter speed, 212

- when to use, 92–94

aperture rating, 94

artifacts, 9, 166

audio, video, 244–246

Auto Bracketing (BKT) mode, 194, 261–263

Auto Cleaning feature, 36–37

Auto Exposure Bracketing feature, 194, 261–263

Auto ISO setting, 8–9, 116–117

Auto mode, 56–57. *See also* automatic modes

Auto setting, 7, 61, 72

autofocus. *See also* focus

- 3D mode, 119–120

- action and, 120

- AF-A mode, 61, 62, 72

- AF-area mode, 118–119

- AF-assist illuminator, 2, 14, 19, 209

- AF-C mode, 72, 118–119

- AF-S mode, 13–14, 72, 142–144

- considerations, 72, 120

- Dynamic Area AF mode, 118–119

- face detection, 146

- Live View Face priority mode, 146

- setting, 13–14

- Single-Point AF mode, 119
- video, 247

autofocus modes, 72

Automatic Exposure Lock (AE-L) function, 141–142, 255

Automatic Focus (AF) points, 118–119

automatic modes, 53–75

Automatic Portrait mode, 136

Autumn Colors mode, 67

B

backgrounds

- backlit, 140, 254

- blurred. *See* blurred backgrounds

- bright, 71
- busy, 115
- considerations, 155
- dark/light, 254, 255
- depth, 188, 226–227
- flash exposure and, 215–216
- in focus, 43, 93, 205
- isolating subjects from, 65, 91, 121
- portraits, 65, 139, 154, 155
- silhouettes and, 71
- backlighting, 140, 254
- Beach/Snow mode, 66
- BKT (Auto Bracketing) mode, 194, 261–263
- black and white images, 144–145, 176–177
- blinkies, 100, 175
- Blossom mode, 68
- blurred backgrounds. *See also* backgrounds
 - action shots and, 87, 88
 - Aperture Priority mode, 115, 136–137
 - Live View and, 181
 - panning and, 88, 124–125
 - portraits, 58, 59, 136
- blurring. *See also* motion
 - aperture size and, 49, 115–116
 - backgrounds. *See* blurred backgrounds
 - considerations, 100
 - depth of field and, 49–50
 - motion blur, 49–50, 115–116, 124–127
 - reducing, 206
 - shutter speed and, 164
 - wide angle lenses and, 43
- bracketing, 73, 195, 261–263
- Bracketing button, 2, 261–263
- brightness, 20, 184
- buffer, 122
- Bulb setting, 258–259

C

- cable release, 165, 210, 259
- cables, HDMI, 246
- camera
 - body, 2–5
 - cleaning sensors, 36–37
 - firmware, 34–35
 - holding properly, 24–25
 - internal memory, 122
 - reviewing shots on, 15–18
 - top 12 list, 1–25
- camera accessories
 - cable release, 165, 210, 259
 - cables, 246
 - filters. *See* filters
 - lenses. *See* lenses
 - tripods. *See* tripods
- camera modes. *See also* specific modes
 - autofocus modes, 72
 - automatic modes, 53–75
 - continuous shooting modes, 122–123
 - display modes, 15–18
 - drive modes, 120
 - effects modes. *See* special effects modes
 - metering modes. *See* metering modes
 - professional. *See* professional modes
 - scenes. *See* scene modes
 - video focus modes, 247
- camera settings, favorite, 99–101
- camera shake, 81–82, 87, 164, 206, 259
- Candlelight mode, 68
- cartoon-like images, 69–70
- catchlight, 147
- Center-weighted mode, 139–141
- CH (Continuous High) shooting mode, 122–123
- Child mode, 64
- children, 64, 148–149, 157. *See also* portraits
- Clean functions, 36–37

- clipping, 20–21
- Close Up mode, 61
- close-ups, 61, 158, 263–264. *See also* macro photography
- Cloudy setting, 7, 169
- color
 - complementary, 232–233
 - composition and, 184, 231
 - contrasting, 232–233
 - cool/warm, 169, 178
 - filters, 176–177
 - saturation, 71, 145, 171–173, 184
- color balance correction, 6
- Color Sketch mode, 69–70
- color temperature, 6
- complementary colors, 232–233
- composition, 223–237
 - angles, 228
 - brightness and, 184
 - color and, 184, 231
 - contrasting elements, 232–233
 - depth and, 188, 226–228
 - frames within frames, 236
 - leading lines, 234
 - overview, 183–184, 223
 - patterns, 230
 - point of view, 229
 - rule of thirds, 181, 185–187, 235
 - sharpness, 184
 - splitting frames, 234–235
- compression, 10, 37–38, 203
- Continuous Drive mode, 120, 122
- Continuous High (CH) shooting mode, 122–123
- continuous shooting modes, 122–123
- Continuous-servo AF (AF-C) mode, 72, 118–119
- contrast, 173, 176, 208, 264, 265
- contrasting elements, 232–233
- control panel, 4
- cropping, 12–13
- Custom Setting menu, 141

D

Dawn/Dusk mode, 65
Daylight setting, 169
Delete button, 3
depth of field
 aperture and, 49, 91–95, 115–116
 backgrounds, 226–227
 composition and, 188, 226–228
 considerations, 91, 115–116
 deep, 93
 isolating subject, 107
 motion and, 49–50
 shallow, 226
 wide-angle lenses and, 43
Depth of Field Preview button, 2
Diopter Adjustment control, 3
Direct Sunlight setting, 7
display modes, 15–18
D-Lighting feature, 71, 73, 265–266
drive modes, 120
Dusk/Dawn mode, 65
Dynamic mode, 62
dynamic range, 38
Dynamic Area AF mode, 118–119

E

editing video, 248
effects modes. *See* special effects modes
environmental portraits, 138–139
EV (exposure value), 47
exposure
 adjusting, 71–72
 AE Lock feature, 141–142, 255
 aperture and, 47
 bracketing, 73, 195, 261–263
 calculating, 48–49
 considerations, 47, 100, 101
 long, 22, 206, 208, 210–211

 overexposure, 71, 100, 194, 196
 overview, 46–49
 reciprocal, 48–49
 Spot metering mode, 254–256
 too dark/light, 254, 261
 underexposure, 72
Exposure Compensation
 button, 4, 23
Exposure Compensation feature
 Auto Exposure bracketing, 195, 261–263
 considerations, 73, 100
 flash, 215–216
 landscape scenes, 173–176
 portraits, 139
 retaining details in
 highlights, 100, 101, 173–176
 Spot metering mode, 255
Exposure Delay mode, 22–23
exposure triangle, 47–48
exposure value (EV), 47
eyes, focusing on, 136, 137, 142–144, 147

F

face detection, 146
faces, 129, 146, 153, 247
fill flash, 146–148
Fill Flash setting, 146–148
filters
 built-in, 176–177
 color, 176–177
 low pass, 243
 monochrome, 144–145
 neutral density, 183
 polarizing, 183
fireworks scenes, 208, 258
firmware updates, 34–35
flash, 212–214
 built-in, 7, 212–214, 219
 considerations, 210, 211, 212, 219
 disabling, 57, 209–210
 exposure compensation, 73, 210, 215–216
 external, 7, 219
 fill, 146–148
 Flash Off mode, 57
 glass and, 219
 hot shoe, 7
 ISO settings and, 203
 metering modes, 213–214
 red-eye reduction, 66, 216–218
 shutter speed and, 212
 sync speed, 212
 using, 212–214
Flash Compensation feature, 73, 210, 215–216
Flash mode button, 2
Flash Off mode, 57
flash range, 213
Flash setting, 7
flowers, 68
fluorescent lighting, 7
Fluorescent setting, 7
focal distance, 179
focal length, 41–46, 225
focus
 3D-tracking mode, 119–120
 action shots, 120–121
 automatic. *See* autofocus
 choosing focus mode, 2, 10–14, 119
 custom options, 19
 dynamic, 118–119
 landscape scenes, 179–182
 with Live View, 181–182
 in low light, 208–210
 manual. *See* manual focus
 on people, 142–144, 146, 147
 pre-focusing, 120–121
 selective, 70
 Servo mode, 118–119
 setting, 13–14
 single-focus point, 12–13, 119, 142–144
 with tripod, 179, 183–184
 video, 240, 247

- Focus Lock selector, 3
- focus mode selector, 2, 10–14
- focus plane, 70
- Focus Point Wrap feature, 19
- focus points, 13–14, 118–120
- Food mode, 67
- food photography, 67
- frame rate, 242, 243
- frames
 - within frames, 236
 - splitting, 234–235
 - using properly, 127–128
- framing portraits, 150, 152, 156
- f-stops, 47, 48–49, 94. *See also* aperture
- Function button, 2

G

- glass, shooting through, 219
- golden hours, 99–100, 171, 178
- golden light, 99–100, 171, 178
- gray card, 139
- grid overlay, 187
- grid, using, 22
- grid, viewfinder, 22

H

- HD (high-definition) video, 242, 246–247
- HDMI cables, 246
- HDMI mini connector, 5
- HDMI ports, 247
- HDR (high dynamic range)
 - images, 193–195
- headphone connector, 5
- headphones, 244
- HFD (hyper focal distance), 179
- High Capacity (SDHC) cards, 32
- high dynamic range (HDR)
 - images, 193–195
- High ISO Speed Noise Reduction feature, 203
- High Key mode, 71
- high-definition (HD) video, 242, 246–247

- high-key images, 71
- Highlight Alert feature,
 - 100–101, 183
- highlights, 100–101, 173–176, 183
- histograms, 20–21
- hot shoe, 7
- hyper focal distance (HFD), 179

I

- i button, 3, 173
- image area, 12–13
- image information, 100
- Image Review button, 246
- image stabilization, 206–207
- image-processing software,
 - 189–192
- images
 - advanced techniques,
 - 251–267
 - black and white, 144–145, 176–177
 - composition. *See* composition
 - cropping, 12–13
 - file size, 10
 - HDR, 193–195
 - high-key, 71
 - information about, 17
 - JPEG, 8–9, 37–41, 194
 - low-key, 72
 - panoramic, 189–192
 - quality settings, 8–9, 10–11, 40
 - RAW, 10, 37–41
 - resolution, 39, 144
 - reviewing on camera, 15–18
- incandescent lighting, 7
- Incandescent setting, 7
- Info button, 3
- information display, 16
- infrared receiver, 2
- interlaced video, 242
- ISO numbers, 47
- ISO settings

- adjusting, 9, 112–114, 202–205
- auto, 8–9, 116–117
- considerations, 8–9, 47, 83, 100, 213
- landscape scenes, 166
- noise and, 114, 116, 166, 202–205
- Programmed Auto mode,
 - 81–85
- selecting, 90
- Shutter Priority mode and,
 - 112–114
 - very high, 204–205
- ISO/Zoom Out/ISO Sensitivity button, 3
- i-TTL, 213–214

J

- JPEG format, 10
- JPEG images, 8–9, 37–41, 194
- JPEG mode, 195
- JPEG option, 8–9

K

- kit lenses, 14–15, 46

L

- Landscape mode, 60
- landscape photography, 161–197
 - advanced techniques,
 - 189–195
 - Autumn Colors mode, 67
 - beach/sand/snow scenes, 66, 97, 254
 - black and white images,
 - 176–177
 - composition, 183–188
 - considerations, 60
 - exposure compensation,
 - 173–176
 - flowers, 68
 - golden light, 99–100, 171, 178
 - ISO settings, 166

- Landscape mode, 60
 - lightning storms, 258
 - nighttime. *See* night shots
 - noise reduction, 167–168
 - panoramas, 189–192
 - saturation, 171–173
 - sense of depth, 188
 - sharpness, 171, 172, 176, 179–182, 184
 - skies, 173–176
 - sunlight. *See* sunlight
 - sunrise/sunset shots, 63, 65, 178, 255–256
 - tripods, 164–165, 179
 - water, 84, 89, 90, 183–184
 - where to focus, 179–180
 - white balance, 169–171
 - Landscape picture control, 171–173
 - LCD display, 15–18
 - leading lines, 234
 - lens flare, 260
 - lens mounting mark, 2
 - lens shade, 260
 - lenses, 41–46
 - aperture rating, 94
 - choosing, 151
 - close-up, 263
 - focal length, 41–46
 - image stabilization, 206
 - kit, 14–15, 46
 - normal, 43–44
 - portraits, 59, 138–139, 151
 - telephoto, 44, 45, 46
 - Vibration Reduction, 206
 - VR, 165
 - wide-angle, 42–43, 138–139
 - zoom, 45, 61, 94, 263–264
 - light meter, 139
 - lighting, 199–221
 - Active D-Lighting, 71, 73, 265–266
 - AF-assist illuminator, 2, 14, 19, 209
 - aperture size and, 94
 - backlighting, 140, 254
 - Candlelight mode, 68
 - catchlight, 147
 - cloudy days, 7
 - daylight, 169
 - fluorescent, 7, 169
 - focusing in low light, 208–210
 - golden hours, 99–100, 171, 178
 - high-key, 71
 - highlights, 100–101, 173–176
 - image stabilization, 206–207
 - incandescent, 7
 - long exposures, 203, 206, 208, 210–211
 - low-key, 72
 - nighttime. *See* night shots
 - overexposure, 71, 100, 194, 196
 - overview, 199
 - portraits, 139–140, 153, 154
 - raising ISO, 202–205
 - red-eye reduction and, 218
 - shade, 7, 169
 - Shutter Priority mode and, 112–114
 - sunlight. *See* sunlight
 - tungsten, 7
 - lightning storms, 258
 - Live View mode
 - close-ups and, 264
 - considerations, 73
 - face detection, 146
 - focusing with, 181–182
 - grid overlay, 187
 - previewing changes, 73
 - previewing scene modes, 73
 - previewing white balance, 159, 170
 - video recording, 240–241
 - Live View selector with LV button, 3
 - Long Exposure Noise Reduction option, 210–211
 - Low Key mode, 72
 - low pass filter, 243
 - low-key images, 72
 - luminance, 20
- ## M
- macro photography, 263–264. *See also* close-ups
 - Main Command dial, 3
 - Manual flash mode, 213–214
 - manual focus
 - for anticipated action, 120–121
 - landscapes, 180, 181, 182
 - Live View and, 181
 - panoramas, 192
 - tips for, 180, 182
 - using, 14–15, 181
 - Manual (M) mode, 95–98
 - advanced techniques, 257–259
 - considerations, 95–96, 99, 100, 257
 - shooting in, 98
 - shutter speed, 212
 - when to use, 96–97
 - Matrix metering mode, 73, 139, 254
 - megapixels, 32, 39
 - memory cards
 - choosing, 32
 - considerations, 122, 203
 - formatting, 32–33
 - high capacity, 32
 - overview, 32
 - updating firmware from, 35
 - video and, 32, 240, 241
 - memory, internal, 122
 - Menu button, 3
 - metadata, 100
 - Meter/Format button, 4
 - metering modes
 - Center-weighted, 139–141
 - considerations, 73, 213–214
 - for flash, 213–214
 - Manual, 213–214
 - Matrix, 139, 254
 - for portraits, 139–141

- Spot, 139, 254–256
 - for sunrise/sunset, 255–256
- microphone, 4, 244–246
- microphone connector, 5
- Miniature Effect mode, 70
- Mirror-up mode, 165
- Mode dial, 4
- Mode dial lock release, 4
- modes. *See* camera modes
- Monitor/LCD, 3
- Monochrome picture control,
 - 144–145, 176–177
- motion. *See also* action shots
 - angle of, 108, 129–130
 - blurring, 49–50, 115–116,
 - 124–127
 - considerations, 105
 - depth of field and, 49–50
 - direction of travel, 108–109,
 - 127–130
 - freezing, 49–50, 62, 86
 - ISO Sensitivity setting,
 - 116–117
 - panning, 88, 124–125
 - portraits and, 148–149
 - showing, 86
 - Sports mode, 62
 - stopping with Shutter Priority, 112–114
 - subject speed, 110
 - vantage point, 129–130
- motion blur, 49–50, 115–116,
 - 124–127. *See also* blurring
- .mov extension, 247
- Movie Record button, 4, 240
- movies. *See* video
- Multi-selector, 15, 17, 101
- Multi-selector with OK button,
 - 3

N

- neutral density (ND) filter, 183
- Night Landscape mode, 66
- Night Portrait mode, 65, 212
- night shots
 - Bulb setting, 258–259

- fireworks, 208, 258
- lightning storms, 258
- long exposures, 208, 210–211
- Night Landscape mode, 66
- Night Portrait mode, 65, 212
- Night Vision mode, 69
- Party/Indoor mode, 66
- Night Vision mode, 69
- Nikon ViewNX-i software, 248
- noise, 9, 62
- noise reduction
 - image file size and, 203
 - ISO settings and, 114, 116,
 - 166, 202–205
 - landscape photography,
 - 167–168
 - long exposures, 210–211
 - setting up for, 167–168

O

- overexposure, 71, 100, 194, 196
- Overview display option, 17

P

- panning, 88, 124–125
- panoramas, 189–192
- Party/Indoor mode, 66
- patterns, 230
- people. *See also* portraits
 - action shots. *See* action shots
 - children, 64, 148–149, 157
 - close-ups, 158
 - eyes, 136, 137, 142–144, 147
 - face detection, 146
 - faces, 129, 146, 153, 247
 - focusing on, 142–144, 146,
 - 147
 - party/indoor shots, 66
 - red-eye reduction, 66,
 - 216–218
 - skin tones, 145–146, 153, 154
- Pet Portrait mode, 68
- Photo Shooting menu, 9, 24
- photography

- action. *See* action shots
- advanced techniques,
 - 251–267
- close-up, 61, 158, 263–264
- composition. *See* composition
- food, 67
- landscape. *See* landscape photography
- macro, 263–264
- portraits. *See* portraits
- sports, 45, 62
- photos. *See* images
- picture controls, 72
- Playback button, 3, 18, 112
- Playback Display options, 15–18
- Playback menu, 15
- playback, video, 246–247
- Playback Zoom In button, 181
- point of view, 229
- polarizing filters, 183
- Portrait control (PT), 145–146
- Portrait mode, 58–59, 136
- portraits, 133–159. *See also* people
 - action shots, 148–149
 - AE Lock feature and,
 - 141–142
 - Aperture Priority mode,
 - 136–139
 - backgrounds, 65, 139, 154,
 - 155
 - black and white, 144–145
 - catchlight, 147
 - children, 64, 148–149, 157
 - close-ups, 158
 - considerations, 133
 - environmental, 138–139
 - face detection, 146
 - fill flash, 146–148
 - focusing on eyes, 142–144,
 - 147
 - framing, 150, 152, 156
 - lenses, 59, 138–139, 151
 - lighting, 139–140, 153, 154
 - metering modes for, 139–141
 - night, 65, 212

- orientation, 150, 152
- pets, 68
- Portrait control (PT), 145–146
- Portrait mode, 58–59, 136
- red-eye reduction, 66, 216–218
- reducing shadows, 146–148
- single-point focusing, 142–144
- skin tones, 140, 145–146, 153, 154
- sunlight and, 153
- tips for, 150–158
- ports, HDMI, 247
- Power switch, 4
- Preset Manual setting, 7
- prime lenses. *See* zoom lenses
- professional modes, 77–103. *See also specific modes*
- Aperture Priority. *See* Aperture Priority mode
- Manual. *See* Manual mode
- overview, 77
- Programmed Auto, 80–85, 212
- Shutter Priority. *See* Shutter Priority mode
- tips for, 99–101
- User Settings, 98–99
- Programmed Auto (P) mode, 80–85, 212
- progressive video, 242
- PT (Portrait control), 145–146

Q

- quality settings, 10–11, 242–243
- Qual/Zoom In/Image Quality button, 3

R

- RAW format, 10, 37–41, 194, 263
- RAW images, 10, 37–41
- RAW mode, 194, 204
- reciprocal change, 47
- reciprocal exposures, 47, 48–49

- Record icon, 240
- recording video. *See* video
- red-eye reduction, 66, 216–218
- reflections, 147, 183, 226, 228
- Release Mode dial, 4, 165
- Release Mode dial lock release, 4
- remote release, 165, 259
- reset button, 23–24
- resolution, 39, 144, 242
- rule of thirds, 181, 185–187, 235

S

- saturation, 145, 171–173, 184
- scene modes, 58–68
 - Active D-Lighting and, 71, 73, 265–266
 - Auto ISO option and, 9
 - autofocus and, 72
 - Beach/Snow, 66
 - Child, 64
 - Close-up, 61
 - considerations, 58, 72–73
 - Food, 67
 - Landscape, 60
 - Night Landscape, 66
 - Night Portrait, 65
 - Party/Indoor, 66
 - Portrait, 58–59
 - previewing with Live View, 73
 - vs. Programmed Auto mode, 81–85
 - Sports, 62
 - using, 58
- screen flicker, 242
- SD cards. *See* memory cards
- SDHC (High Capacity) cards, 32
- Selective Color mode, 71
- self-timer, 23, 207
- sensors, cleaning, 36–37
- Servo mode, 118–119
- Shade setting, 7, 169
- shadows, 146–148, 257, 264, 265
- shake, camera, 81–82, 87, 164, 206, 259
- shapes, 233

- sharpness
 - black-and-white portraits, 144–145
 - considerations, 92, 184, 206
 - landscapes, 171, 172, 176, 179–182, 184
 - RAW images and, 38–39
 - remote/cable release, 165, 259
 - tack sharp, 135, 179, 181, 183
 - tips for, 179
 - tripods and, 206
- Sharpness setting, 145
- shutter delay options, 22–23
- Shutter Priority (S) mode
 - vs. Aperture mode, 115–116
 - considerations, 87–91, 100, 112–114
 - flash and, 212
 - light levels and, 112–114
 - overview, 85–87
 - shooting in, 90–91
 - shutter speed, 212
 - stopping motion with, 112–114
 - when to use, 87–91
- Shutter Release button, 4
- shutter speed
 - action shots and, 49, 50, 106, 108–117
 - aperture and, 210
 - Bulb setting, 258–259
 - considerations, 98, 100
 - described, 47
 - direction of travel and, 108–109
 - fast, 82–84, 87, 88, 112, 115, 212
 - flash and, 212
 - ISO Sensitivity setting, 116–117
 - isolating subject, 115–116
 - long exposures, 203, 206, 208, 210–211, 212
 - motion blur, 126–127
 - Programmed Auto mode, 80–85, 212
 - self-timer, 207

- slow, 87–90, 100, 164, 203, 206
- stopping motion, 112–114
- subject speed, 110
- subject-to-camera distance, 111
- tripods, 164, 179, 203, 206, 210–211
- Silhouette mode, 71
- silhouetted subjects, 96, 97
- Single-Frame drive mode, 120, 122
- Single-Point AF mode, 119
- single-point focusing, 12–13, 119, 142–144
- Single-servo AF (AF-S) mode, 13–14, 72, 142–144
- skies, 173–176
- skin tones, 140, 145–146, 153, 154
- snow scenes, 66, 97, 254
- software
 - image-processing, 189–192
 - Nikon ViewNX-i, 38, 248
 - for RAW files, 39
- sound, video, 244–246
- speaker, 3
- special effects modes, 69–72
 - Color Sketch, 69–70
 - considerations, 7
 - High Key, 71
 - Low Key, 72
 - Miniature Effect, 70
 - Night Vision mode, 69
 - overview, 71
 - Selective Color, 71
 - Silhouette, 71
- Sports mode, 62
- sports photography, 45, 62
- spot metering, 139, 254–256
- star trails, photographing, 258–259
- starburst effect, 260
- stereo microphone, 4
- Sub-command dial, 2
- subject-to-camera distance, 111
- sunburst, 93

- sunlight
 - considerations, 7
 - creative shots with, 255–256
 - direct, 7
 - lens flare, 260
 - portraits and, 153
 - starbursts, 260
- sunrise shots, 65, 178, 255–256
- Sunset mode, 63
- sunset shots, 63, 178, 255–256
- sync speed, 211

T

- tack-sharp photos, 135, 179, 181, 183
- telephoto lenses, 44, 45, 46
- Through the Lens (TTL) metering, 213–214
- timers
 - recording time, 240
 - self-timers, 23, 207
- tonal ranges, 173
- tones, 20
- tripods
 - Bulb setting, 259
 - considerations, 164, 165
 - focusing and, 179, 183–184
 - HDR images, 194
 - image sharpness, 206
 - image stabilization, 206
 - landscape scenes, 164–165, 179
 - long exposures, 210, 211
 - for macro photography, 264
 - panoramic images, 189, 192
 - shutter speed, 164, 179, 203, 206, 210–211
 - video, 241
 - VR lenses and, 165
- TTL (Through the Lens) metering, 213–214
- tungsten, 7

U

- U1/U2 settings, 98–99

- USB connector, 5
- user settings, 98–99
- User Settings mode, 98–99

V

- Vibration Reduction (VR) lens, 165, 206
- video, 239–249
 - 1080i, 242
 - 1080p, 242
 - autofocus, 247
 - editing, 248
 - focus modes, 247
 - focusing camera, 240
 - frame rate, 242, 243
 - frame size, 242
 - handheld, 241
 - high-definition, 242, 246–247
 - interlaced, 242
 - memory cards, 32, 240, 241
 - playback, 246–247
 - progressive, 242
 - quality, 240, 242–243
 - recording for Internet, 242
 - recording with Live View, 240–241
 - resolution, 144, 242
 - screen flicker, 242
 - sound, 244–246
 - tripods, 241

W

- water, 84, 89, 90, 183–184
- white balance, 6–8, 72, 169–171
- White Balance/Help/Protect button, 3
- wide-angle lenses, 42–43, 138–139
- wildlife, 45, 92, 243

Z

- zoom lenses, 45, 61, 94, 263–264
- zooming in/out, 112, 141, 158